

AD-A182 066

INTEGRATED INFORMATION SUPPORT SYSTEM (IIS) VOLUME 7  
COMMUNICATIONS SUBS (U) GENERAL ELECTRIC CO  
SCHENECTADY NY PRODUCTION RESOURCES CONSU


1/1


UNCLASSIFIED

01 NOV 85 DS-620143300

D PAYME  
F/G 12/6

NL







**AD-A182 066**

**DTIC FILE COPY**

**AFWAL-TR-86-4006  
Volume VII  
Part 4**



**INTEGRATED INFORMATION  
SUPPORT SYSTEM (IISS)  
Volume VII - Communications Subsystem  
Part 4 - IBM IHC and IPC Development Specification**

**General Electric Company  
Production Resources Consulting  
One River Road  
Schenectady, New York 12345**

**Final Report for Period 22 September 1980 - 31 July 1985  
November 1985**

**Approved for public release; distribution is unlimited.**


**MATERIALS LABORATORY  
AIR FORCE WRIGHT AERONAUTICAL LABORATORIES  
AIR FORCE SYSTEMS COMMAND  
WRIGHT-PATTERSON AFB, OH 45433-6533**

# NOTICE

When Government drawings, specifications, or other data are used for any purpose other than in connection with a definitely related Government procurement operation, the United States Government thereby incurs no responsibility nor any obligation whatsoever; and the fact that the government may have formulated, furnished, or in any way supplied the said drawings, specifications, or other data, is not to be regarded by implication or otherwise as in any manner licensing the holder or any other person or corporation, or conveying any rights or permission to manufacture, use, or sell any patented invention that may in any way be related thereto.


This report has been reviewed by the Office of Public Affairs (ASD/PA) and is releasable to the National Technical Information Service (NTIS). At NTIS, it will be available to the general public, including foreign nations.

This technical report has been reviewed and is approved for publication.

  
\_\_\_\_\_  
DAVID L. JUDSON, PROJECT MANAGER  
AFWAL/MLTC  
WRIGHT PATTERSON AFB OH 45433

5 Aug 1986  
\_\_\_\_\_  
DATE

FOR THE COMMANDER:

  
\_\_\_\_\_  
GERALD C. SHUMAKER, BRANCH CHIEF  
AFWAL/MLTC  
WRIGHT PATTERSON AFB OH 45433

7 Aug 86  
\_\_\_\_\_  
DATE

"If your address has changed, if you wish to be removed from our mailing list, or if the addressee is no longer employed by your organization please notify AFWAL/MLTC, W-PAFB, OH 45433 to help us maintain a current mailing list."

Copies of this report should not be returned unless return is required by security considerations, contractual obligations, or notice on a specific document

Unclassified

SECURITY CLASSIFICATION OF THIS PAGE

A182 166

## REPORT DOCUMENTATION PAGE

1a. REPORT SECURITY CLASSIFICATION Unclassified		1b. RESTRICTIVE MARKINGS	
2a. SECURITY CLASSIFICATION AUTHORITY		3. DISTRIBUTION/AVAILABILITY OF REPORT  Approved for public release; distribution is unlimited.	
2b. DECLASSIFICATION/DOWNGRADING SCHEDULE			
4. PERFORMING ORGANIZATION REPORT NUMBER(S)		5. MONITORING ORGANIZATION REPORT NUMBER(S)  AFVAL-TR-86-40006 Vol VII, Part 4	
6a. NAME OF PERFORMING ORGANIZATION General Electric Company Production Resources Consulting	6b. OFFICE SYMBOL (If applicable) AFVAL/MLTC	7a. NAME OF MONITORING ORGANIZATION AFVAL/MLTC	
6c. ADDRESS (City, State and ZIP Code) 1 River Road Schenectady, NY 12345		7b. ADDRESS (City, State and ZIP Code) WPAFB, OH 45433-6535	
8a. NAME OF FUNDING/SPONSORING ORGANIZATION Materials Laboratory Air Force Systems Command, USAF	8b. OFFICE SYMBOL (If applicable) AFVAL/MLTC	9. PROCUREMENT INSTRUMENT IDENTIFICATION NUMBER F33615-80-C-8155	
8c. ADDRESS (City, State and ZIP Code) Wright-Patterson AFB, Ohio 45433		10. SOURCE OF FUNDING NOS.	
		PROGRAM ELEMENT NO. 78011F	PROJECT NO. 7500
		TASK NO. 62	WORK UNIT NO. 01
11. TITLE (Include Security Classification) (See Reverse)			
12. PERSONAL AUTHOR(S) Payne, Diane			
13a. TYPE OF REPORT Final Technical Report	13b. TIME COVERED 22 Sept 1980 - 31 July 1985	14. DATE OF REPORT (Yr., Mo., Day) 1985 November	15. PAGE COUNT 87
16. SUPPLEMENTARY NOTATION ICAN Project Priority 6201		The computer software contained herein are theoretical and/or references that in no way reflect Air Force-owned or -developed computer software.	
17. COSATI CODES		18. SUBJECT TERMS (Continue on reverse if necessary and identify by block number)	
FIELD	GROUP	SUB GR	
1308	0905		
19. ABSTRACT (Continue on reverse if necessary and identify by block number)  This development specification describes the basic architecture of the IBM interface, including the inter-host communications primitives and the inter-process communications primitives. (S-04280) (C-0000)			
20. DISTRIBUTION/AVAILABILITY OF ABSTRACT UNCLASSIFIED/UNLIMITED <input checked="" type="checkbox"/> SAME AS RPT. <input type="checkbox"/> DTIC USERS <input type="checkbox"/>		21. ABSTRACT SECURITY CLASSIFICATION Unclassified	
22a. NAME OF RESPONSIBLE INDIVIDUAL David L. Judson		22b. TELEPHONE NUMBER (Include Area Code) 513-285-6976	22c. OFFICE SYMBOL AFVAL/MLTC

11. Title

Integrated Information Support System (IISS)  
Vol VII - Communications Subsystem  
Part 4 - IBM IHC and IPC Development Specification

A S D 86 0018  
9 Jan 1986

Accession For	
NTIS CRA&I	<input checked="checked" type="checkbox"/>
DTIC TAB	<input type="checkbox"/>
Unannounced	<input type="checkbox"/>
Justification .....	
By .....	
Distribution/ .....	
Availability Codes	
Dist	Avail and/or Special
A-1	



## PREFACE

This development specification covers the work performed under Air Force Contract F33615-80-C-5155 (ICAM Project 6201). This contract is sponsored by the Materials Laboratory, Air Force Systems Command, Wright-Patterson Air Force Base, Ohio. It was administered under the technical direction of Mr. Gerald C. Shumaker, ICAM Program Manager, Manufacturing Technology Division, through Project Manager, Mr. David Judson. The Prime Contractor was Production Resources Consulting of the General Electric Company, Schenectady, New York, under the direction of Mr. Alan Rubenstein. The General Electric Project Manager was Mr. Myron Hurlbut of Industrial Automation Systems Department, Albany, New York.

Certain work aimed at improving Test Bed Technology has been performed by other contracts with Project 6201 performing integrating functions. This work consisted of enhancements to Test Bed software and establishment and operation of Test Bed hardware and communications for developers and other users. Documentation relating to the Test Bed from all of these contractors and projects have been integrated under Project 6201 for publication and treatment as an integrated set of documents. The particular contributors to each document are noted on the Report Documentation Page (DD1473). A listing and description of the entire project documentation system and how they are related is contained in document FTR620100001, Project Overview.

The subcontractors and their contributing activities were as follows:

### TASK 4.2

<u>Subcontractors</u>	<u>Role</u>
Boeing Military Aircraft Company (BMAC)	Reviewer
D. Appleton Company (DACOM)	Responsible for IDEF support, state-of-the-art literature search
General Dynamics/ Ft. Worth	Responsible for factory view function and information models

DS 620143300  
1 November 1985

<u>Subcontractors</u>	<u>Role</u>
Illinois Institute of Technology	Responsible for factory view function research (IITRI) and information models of small and medium-size business
North American Rockwell	Reviewer
Northrop Corporation	Responsible for factory view function and information models
Pritsker and Associates	Responsible for IDEF2 support
SofTech	Responsible for IDEFO support

TASKS 4.3 - 4.9 (TEST BED)

<u>Subcontractors</u>	<u>Role</u>
Boeing Military Aircraft Company (BMAC)	Responsible for consultation on applications of the technology and on IBM computer technology.
Computer Technology Associates (CTA)	Assisted in the areas of communications systems, system design and integration methodology, and design of the Network Transaction Manager.
Control Data Corporation (CDC)	Responsible for the Common Data Model (CDM) implementation and part of the CDM design (shared with DACOM).
D. Appleton Company (DACOM)	Responsible for the overall CDM Subsystem design integration and test plan, as well as part of the design of the CDM (shared with CDC). DACOM also developed the Integration Methodology and did the schema mappings for the Application Subsystems.

DS 620143300  
1 November 1985

Subcontractors

Role

Digital Equipment  
Corporation (DEC)

Consulting and support of the  
performance testing and on DEC  
software and computer systems  
operation.

McDonnell Douglas  
Automation Company  
(McAuto)

Responsible for the support and  
enhancements to the Network  
Transaction Manager Subsystem  
during 1984/1985 period.

On-Line Software  
International (OSI)

Responsible for programming the  
Communications Subsystem on the  
IBM and for consulting on the  
IBM.

Rath and Strong Systems  
Products (RSSP) (In 1985  
became McCormack & Dodge)

Responsible for assistance in  
the implementation and use of  
the MRP II package (PIOS) that  
they supplied.

SofTech, Inc.

Responsible for the design and  
implementation of the Network  
Transaction Manager (NTM) in  
1981/1984 period.

Software Performance  
Engineering (SPE)

Responsible for directing the  
work on performance evaluation  
and analysis.

Structural Dynamics  
Research Corporation  
(SDRC)

Responsible for the User  
Interface and Virtual Terminal  
Interface Subsystems.

Other prime contractors under other projects who have  
contributed to Test Bed Technology, their contributing  
activities and responsible projects are as follows:

Contractors

ICAM Project

Contributing Activities

Boeing Military  
Aircraft Company  
(BMAC)

1701, 2201,  
2202

Enhancements for IBM  
node use. Technology  
Transfer to Integrated  
Sheet Metal Center  
(ISMC)

DS 620143300  
1 November 1985

<u>Contractors</u>	<u>ICAM Project</u>	<u>Contributing Activities</u>
Control Data Corporation (CDC)	1502, 1701	IISS enhancements to Common Data Model Processor (CDMP)
D. Appleton Company (DAGOM)	1502	IISS enhancements to Integration Methodology
General Electric	1502	Operation of the Test Bed and communications equipment.
Hughes Aircraft Company (HAC)	1701	Test Bed enhancements
Structural Dynamics Research Corporation (SDRC)	1502, 1701, 1703	IISS enhancements to User Interface/Virtual Terminal Interface (UI/VTI)
Systran	1502	Test Bed enhancements. Operation of Test Bed.

# TABLE OF CONTENTS

		<u>Page</u>
SECTION 1.0	BASIC ARCHITECTURE .....	1-1
SECTION 2.0	MODULE LINKED TO COMM, NTM AND APS ....	2-1
2.1	OSIIBM .....	2-1
SECTION 3.0	INTER-PROCESS PRIMITIVES (IPC) .....	3-1
3.1	Create Mailbox .....	3-1
3.2	Send Message .....	3-3
3.3	Receive Message .....	3-4
3.4	Get Message .....	3-6
3.5	Delete Mailbox .....	3-8
3.6	Release Event Block .....	3-9
3.7	Set Timer .....	3-9
3.8	Cancel Timer .....	3-10
3.9	Wait for an Event .....	3-11
3.10	Log an Error Message .....	3-14
3.11	Terminate Processing .....	3-14
SECTION 4.0	PROCESS CONTROL PRIMITIVES (PRC) .....	4-1
4.1	Create Process .....	4-1
4.2	Delete Process .....	4-3
4.3	Get Process Name .....	4-4
SECTION 5.0	PRC SUPPORT ROUTINES .....	5-1
5.1	ATTACH Stub .....	5-1
5.2	End-of-Task Exit .....	5-1
SECTION 6.0	ENVIRONMENT CONTROL MODULES .....	6-1
6.1	MVS Initialization .....	6-1
6.2	Common Table .....	6-2
SECTION 7.0	INTER-HOST PRIMITIVES (IHC) .....	7-1
7.1	Initialize Communication with the VAX or Honeywell Level 6 ..	7-1
7.2	Transmit a Message to the VAX or Honeywell Level 6 ....	7-2
7.3	Receive a Message from the VAX or Honeywell Level 6 ..	7-3
7.4	Get a Message from the VAX or Honeywell Level 6 ..	7-5
7.5	Cancel a Receive from the VAX or Honeywell Level 6 ..	7-6

TABLE OF CONTENTS (Continued)

		<u>Page</u>
7.6	Terminate Communication with the VAX or Honeywell Level 6 ..	7-7
SECTION 8.0	INTERFACE TO CICS APPLICATION .....	8-1
8.1	Pseudo-AP .....	8-1
SECTION 9.0	CICS INTERFACE PRIMITIVES .....	9-1
9.1	Initialize Communication with CICS ..	9-1
9.2	Send Message to CICS .....	9-3
9.3	Receive Message from CICS .....	9-4
9.4	Get a Message from CICS .....	9-5
9.5	Cancel Receive from CICS .....	9-7
9.6	Terminate Communication with CICS ...	9-7
SECTION 10.0	3270 EMULATOR .....	10-1
APPENDIX A	MAILBOX LOGIC .....	A-1
APPENDIX B	MODULE STRUCTURE CHART .....	B-1
APPENDIX C	VTAM LOGIC FOR IHC .....	C-1

DS 620143300  
1 November 1985

## INTRODUCTION

This manual does not follow the normal format of a Development Specification because the information herein involves interfaces with commercially available communications and operating systems.

## SECTION 1

### BASIC ARCHITECTURE OF THE IBM INTERFACE

The IBM Interface consists of the following programs:

1. The OSIIBM stub, which must be link-edited with all programs in the system, including the COMM, NTM, QP, and AP programs. It contains entry points for all the primitive routines and invokes the proper interface program to perform the requested function. It also contains the primitive routine ENDRUN.
2. The OSIIPC program which contains:
  - CRTMBX, for creating a mailbox
  - DELMBX, for deleting a mailbox
  - SNDMSG, for sending a message to a mailbox
  - RCVMSG and GETMSG, for receiving a message from a mailbox
  - SETTIM, for setting a timer
  - CNLTIM, for cancelling a timer, and
  - WAIT01 thru WAIT22, for waiting for completion of one event out of a list of events
3. The OSIPRC program which contains:
  - CRTPRC, for creating a process (subtask)
  - DELPRC, for deleting a process
  - GETNAM, for providing a process with its own process name
4. The OSIIHC program (and its error exit IHCEXT) which contains:
  - INILAN, for initiating communication with the VAX or Level 6

- TRMLAN, for terminating communication with the VAX or Level 6
  - XMTLAN, for sending a message to the VAX or Level 6
  - RCVLAN and GETLAN, for receiving a message from the VAX or Level 6
  - CNLLAN, for cancelling a receive from the VAX or Level 6
5. The VTAM control block modules, which are assembled from macro calls, and which contain the VTAM control blocks and other data required to communicate with the VAX or Level 6. Two of these modules must be created -- one for the VAX and one for the Level 6. The load module names are the same as the port names.
6. The error logging programs:
- OSIERR, which contains ERRPRO, which formats and time-stamps error messages and sends them to the error log mailbox
  - ERRLOG\*, which writes error messages to the error log (\* this program will be implemented by GE)
7. The PRC support routines:
- OSIATCH, the ATTACH stub, which is the first program to get control when a subtask is created; it obtains the work areas required by the IBM Interface programs
  - OSIETXR, the End-of-Task exit, which searches for and removes any remaining table entries for a subtask when it ends
8. The environment control modules and tables:
- OSIMVSI, which is the first program executed in the address space, and which initializes the environment
  - OSICOMTB, the COMMON TABLE, which contains other tables with information required by all the

primitives, as well as data required to initialize the address space. The COMMON TABLE is assembled from macro calls.

All the IBM interface modules are coded in Assembler, and all are re-entrant. The COMMON TABLE and the VTAM control block modules must also be link-edited as re-entrant, even though they are in fact modified during execution.

NOTE: The following modules are part of the IBM Interface, but they are not being implemented by On-Line Software. For this reason, they are not described in this document.

9. The Console Primitive program which handles:

- Initiating and terminating communication with a terminal
- Sending and receiving messages to/from a terminal

\*\* As a temporary measure, an interface program is being provided which accepts the console primitive calls and invokes the IHC program to communicate with a terminal.

10. The modules required to run a transaction in a CICS region

- The Psuedo-AP
- The CICS Interface program
- The 3270 Emulator program
- The VTAM SLU control block table with entries for as many terminals as are concurrently being emulated

## SECTION 2

### MODULE LINKED TO COMM, NTM AND APS

#### 2.1 OSIIBM

Entry from the IISS TEST BED programs into the IBM interface is accomplished through COBOL calls which are resolved in a stub module (OSIIBM) which must be link-edited to each COMM, NTM and AP program. This module has multiple entry points, one for each primitive which a program can call.

The entry points are:

CRTMBX	SETTIM	ERRPRO	CRTPRC	COMM only:
SNDMSG	CNLTIM	ENDRUN	DELPRC	INILAN
RCVMSG	WAIT01		GETNAM	XMTLAN
GETMSG	thru			RCVLAN
DELMBX	WAIT22			GETLAN
RELEVB				CNLLAN
				TRMLAN

#### FUNCTIONS PERFORMED:

##### A. RECEIVE CONTROL AT AN ENTRY POINT

1. Save the COBOL program's registers
2. Record the type of call

##### B. SET UP TO PASS CONTROL

1. Locate the Task Work Area (TWA) by searching back through the save area chain
2. Save in the TWA:
  - type of call
  - address of the parameter list (from the COBOL program)

##### C. LINK TO THE PRIMITIVES

1. If an IPC, PRC, or IHC call,  
LINK to appropriate interface program

DS 620143300  
1 November 1985

2. If an ERRPRO call,  
set up ERRPRO parameter list in the TWA LINK  
to OSIERR
3. When control is returned,  
restore the COBOL program's registers  
RETURN to caller

D. TERMINATE THE COBOL PROGRAM

1. If an ENDRUN call,  
restore the ATTACH stub's registers (from the  
TWA)  
RETURN to ATTACH stub  
(process is ended)

### SECTION 3

#### INTER-PROCESS PRIMITIVES (IPC)

##### 3.1 Create Mailbox

The CRTMBX primitive routine is in program OSIIPC.

CALL 'CRTMBX' USING INPUT-MAILBOX-NAME  
MAILBOX-SIZE  
EVENT-BLOCK-nn  
STATUS.

##### **FUNCTIONS PERFORMED:**

###### **A. VALIDATE PARAMETERS**

1. If mailbox-name has embedded blanks  
set 'invalid mailbox name' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller
2. If mailbox-size is zero  
set 'mailbox size zero' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller
3. If mailbox-size is not numeric or is greater than  
the max  
set 'mailbox size greater than maximum'  
STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller
4. If EVENT-BLOCK is not all zeros  
set 'event block not initialized' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller

###### **B. CHECK IF MAILBOX ALREADY EXISTS**

1. Serialize use of mailbox and MAILBOX TABLE
2. Load address of COMMON TABLE from TWA
3. Search for mailbox-name in MAILBOX TABLE

search til high-water-mark  
some slots may be empty  
follow chain-address if any  
if found empty slot  
    save address of first empty slot

4. If found mailbox-name  
    set 'mailbox already exists' STATUS-CODE  
    LINK to ERRPRO to log error  
    release use of mailbox  
        and MAILBOX TABLE  
    RETURN to caller

C. ESTABLISH MAILBOX

1. Allocate MAILBOX TABLE entry  
    if no empty slot found  
    GETMAIN storage for continuation of MAILBOX  
    TABLE  
    chain and format storage obtained  
    LINK to ERRPRO to record overflow
2. Create mailbox and MAILBOX TABLE entry  
    GETMAIN storage of mailbox-size  
    format mailbox header  
    put mailbox-name, A(storage), A(ECB) in MAILBOX  
    TABLE entry  
    save address of MAILBOX TABLE entry in EVENT-BLOCK

D. PRIME EVENT-BLOCK AND OTHER REQUIRED AREAS

1. Move the mailbox-name to the EVENT-BLOCK  
    (marks it as the EVENT-BLOCK for this task's input  
    mailbox)
2. Set EVENT-TYPE to 01 (RECEIVE)

E. RETURN CONTROL TO CALLER

1. Set 'successful completion' STATUS-CODE
2. Release use of mailbox and MAILBOX TABLE
3. RETURN to caller

### 3.2 Send Message

The SNDMSG primitive routine is in program OSIIPC.

CALL 'SNDMSG' USING TARGET-MAILBOX-NAME  
                  BUFFER  
                  NUMBER-OF-BYTES  
                  EVENT-BLOCK-nn  
                  STATUS.

#### FUNCTIONS PERFORMED:

##### A. VALIDATE PARAMETERS

1. If mailbox-name has embedded blanks  
   set 'invalid mailbox name' STATUS-CODE  
   LINK to ERRPRO to log error  
   RETURN to caller
2. If number-of-bytes is zero  
   set 'number of bytes zero' STATUS-CODE  
   LINK to ERRPRO to log error  
   RETURN to caller
3. If number-of-bytes is not numeric or is greater  
   than the max  
   set 'number of bytes greater than maximum'  
   STATUS-CODE  
   LINK to ERRPRO to log error  
   RETURN to caller

##### B. CHECK EVENT-BLOCK

1. If EVENT-BLOCK is not all zeros  
   set 'event block not initialized' STATUS-CODE  
   LINK to ERRPRO to log error  
   RETURN to caller

##### C. CHECK IF TARGET MAILBOX EXISTS

1. Serialize use of mailbox
2. Load address of COMMON TABLE from TWA (contains  
   MAILBOX TABLE)
3. Search for mailbox-name in MAILBOX TABLE  
   search til high-water-mark

follow chain-address if any  
may be empty slots

4. If not found mailbox-name  
set 'mailbox not found' STATUS-CODE  
LINK to ERRPRO to log error  
release use of mailbox  
RETURN to caller
5. Mailbox found  
save MAILBOX TABLE entry address in EVENT-BLOCK  
(to save future search)

D. PUT MESSAGE IN TARGET MAILBOX

1. Pick up address of storage for mailbox
2. If message doesn't fit in mailbox  
set 'mailbox full' STATUS-CODE  
LINK to ERRPRO to log error  
release use of mailbox  
RETURN to caller
3. Put message in mailbox
4. Adjust current byte-count and displacements
5. POST the ECB in the target mailbox EVENT-BLOCK  
(ECB address is in MAILBOX TABLE entry)

E. RETURN CONTROL TO CALLER

1. Set "successful completion' STATUS-CODE
2. Release use of mailbox
3. RETURN to caller

3.3 Receive Message

The RCVMSG primitive routine is in program OSIIPC.

CALL 'RCVMSG' USING INPUT-MAILBOX-NAME  
EVENT-NUMBER  
EVENT-BLOCK-nn  
STATUS.

FUNCTIONS PERFORMED:

A. VALIDATE PARAMETERS

1. If event-number is zero  
set 'event number zero' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller
2. If event-number is not numeric or is greater than  
maximum  
set 'event number greater than maximum'  
STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller

B. CHECK EVENT-BLOCK

1. If mailbox-name doesn't match that in EVENT-BLOCK  
set 'invalid event block for mailbox named'  
STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller
2. If EVENT-TYPE is not 01 (RECEIVE)  
set 'not a receive event block' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller
3. If EVENT-OUTSTANDING is 01 (event is outstanding)  
set 'only one outstanding receive permitted'  
STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller

C. CHECK IF MAILBOX EXISTS

1. Serialize use of mailbox
2. Load address of COMMON TABLE from TWA (contains  
MAILBOX TABLE)
3. Point to MAILBOX TABLE entry (address saved in  
EVENT-BLOCK)
4. If entry not for this mailbox  
set a 'system-dependent error' STATUS-CODE

LINK to ERRPRO to log error  
Release use of mailbox  
RETURN to caller

5. If previous RECEIVE was returned (implied cancel)  
remove the first message from the mailbox

D. PRIME EVENT-BLOCK

1. Set EVENT-NUMBER to that passed,  
OUTSTANDING-EVENT to 01

E. RETURN CONTROL TO CALLER

1. Set 'successful completion' STATUS-CODE
2. Release use of mailbox
3. RETURN to caller

3.4 Get Message

The GETMSG primitive routine is in program OSIIPC.

CALL 'GETMSG' USING INPUT-MAILBOX-NAME  
BUFFER  
BUFFER-SIZE  
NUMBER-OF-BYTES  
EVENT-BLOCK-nn  
STATUS.

FUNCTIONS PERFORMED:

A. VALIDATE PARAMETERS

1. If buffer-size is zero  
set 'buffer size zero' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller
2. If buffer-size is not numeric or greater than max  
set 'buffer size greater than maximum' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller

B. CHECK EVENT-BLOCK

1. If mailbox-name doesn't match that in EVENT-BLOCK  
set 'invalid event block for mailbox named'  
STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller
2. If EVENT-TYPE is not 01 (RECEIVE)  
set 'not a receive event block' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller
3. If EVENT-OUTSTANDING is zero (no event  
outstanding)  
set 'no receive outstanding' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller

C. READ FIRST MESSAGE FROM MAILBOX

1. Serialize on mailbox
2. Find mailbox  
address of MAILBOX TABLE entry in EVENT-BLOCK  
address of mailbox in MAILBOX TABLE entry
3. If current byte-count equals zero  
set 'receive not satisfied' STATUS-CODE  
LINK to ERRPRO to log error  
release use of mailbox  
RETURN to caller
4. If first message is longer than buffer-size  
set 'buffer too small' STATUS-CODE  
LINK to ERRPRO to log error  
clear buffer to blanks  
  
else (data is lost)  
  
move first message to caller's buffer  
set number-of-bytes to length of message  
set 'successful completion' STATUS-CODE
5. Remove message read from mailbox  
subtract message length from current-byte-count  
adjust displacements

D. CLEAR OUTSTANDING RECEIVE

1. Set OUTSTANDING-EVENT to 00
2. Clear ECB in EVENT-BLOCK

E. RETURN CALL TO CALLER

1. Release use of mailbox
2. RETURN to caller

3.5 Delete Mailbox

The DELMBX primitive routine is in program OSIIPC.

CALL 'DELMBX' USING INPUT-MAILBOX-NAME  
EVENT-BLOCK-nn  
STATUS.

FUNCTIONS PERFORMED:

A. CHECK EVENT-BLOCK

1. If mailbox-name doesn't match that in EVENT-BLOCK  
set 'invalid event block for mailbox named'  
STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller
2. If EVENT-TYPE is not 01 (RECEIVE)  
set 'not a receive event block' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller

B. DELETE MAILBOX

1. Serialize on mailbox and MAILBOX TABLE
2. Find mailbox entry in MAILBOX TABLE
3. Remove MAILBOX TABLE entry
4. FREEMAIN mailbox storage

C. RELEASE THE EVENT-BLOCK

1. Re-initialize the EVENT-BLOCK to character 0's

D. RETURN CONTROL TO CALLER

1. Set 'successful completion' STATUS-CODE
2. Release control of mailbox and MAILBOX CODE
3. RETURN to caller

3.6 Release Event Block

The RELEVB primitive routine is in program OSIIPC

CALL 'RELEVB' USING MAILBOX-NAME      (not used in IBM Interface)  
  EVENT-BLOCK  
  STATUS.

FUNCTIONS PERFORMED:

A. RELEASE THE EVENT-BLOCK

1. Re-initialize the EVENT-BLOCK to character 0's

B. RETURN CONTROL TO CALLER

1. Set 'successful completion' STATUS-CODE
2. RETURN to caller

3.7 Set Timer

The SETTIM primitive routine is in program OSIIPC.

CALL 'SETTIM' USING TIME-INTERVAL  
  EVENT-NUMBER  
  EVENT-BLOCK-nn  
  STATUS.

FUNCTIONS PERFORMED:

A. VALIDATE PARAMETERS

1. If event-number is zero  
    set 'event number zero' STATUS-CODE  
    LINK to ERRPRO to log error  
    RETURN to caller

2. If event-number is not numeric or is greater than 22  
set 'event number greater than maximum'  
STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller
  3. If interval requested is zero  
set 'time interval zero' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller
  4. If interval requested is not numeric or is greater than 235959  
set 'time interval greater than maximum'  
STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller
- B. CHECK EVENT-BLOCK
1. If EVENT-BLOCK is not all zeros  
set 'event block not initialized' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller
- C. PRIME EVENT-BLOCK AND OTHER CONTROL AREAS
1. Set EVENT-NUMBER to that specified,  
EVENT-TYPE to 02 (TIMER)  
EVENT-OUTSTANDING to 01
  2. Store address of Timer EVENT-BLOCK in TWA
  3. Calculate actual expiration time and store in TWA
  4. Store address of timer ECB (in TASK LIST TABLE) in TWA
- D. RETURN CONTROL TO CALLER
1. Set 'successful completion' STATUS-CODE
  2. RETURN to caller

3.8 Cancel Timer

The CNLTIM primitive routine is in program OSIIPC.

CALL 'CNLTIM' USING EVENT-BLOCK-nn  
STATUS.

**FUNCTIONS PERFORMED:**

**A. VALIDATE PARAMETERS**

1. If EVENT-TYPE is not 02 (timer)  
set 'not a timer event block' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller

**B. CANCEL TIMER REQUEST**

1. Clear the TWA timer-related fields
2. Re-initialize the EVENT-BLOCK (character 0's)

**C. RETURN CONTROL TO CALLER**

1. Set 'successful completion' STATUS-CODE
2. RETURN to caller

**3.9 Wait for an Event**

The WAITnn primitive routine is in program OSIIPC.

CALL 'WAITnn' USING EVENT-NUMBER  
STATUS  
NUMBER-OF-EVENT-BLOCKS  
EVENT-BLOCK-nn  
...  
EVENT-BLOCK-mm.

**FUNCTIONS PERFORMED:**

**A. VALIDATE PARAMETERS**

1. If number-of-event-blocks is zero  
set 'number of event blocks zero' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller
2. If number-of-event-blocks is not numeric or is

greater than 22  
set 'number of event blocks greater than max'  
STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller

B. FIND THE ACTIVE EVENT-BLOCKS (THOSE WITH OUTSTANDING EVENTS)

1. If fewer EVENT-BLOCKS are passed than  
NUMBER-OF-EVENT-BLOCKS  
set 'fewer event blocks passed than count'  
STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller
2. If no active EVENT-BLOCKS  
set 'no requests outstanding' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller
3. If any duplicate EVENT-NUMBERS among the active  
EVENT-BLOCKS  
set 'event numbers not unique' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller

C. CHECK EACH ACTIVE EVENT-BLOCK FOR ALREADY-COMPLETED EVENTS

1. TIMER event:  
check expiration time against current time  
if elapsed  
If EVENT-NUMBER is lowest of those completed  
save EVENT-NUMBER and address of EVENT-BLOCK  
else  
issue STIMER REAL with exit routine.  
STIMEXIT, which posts timer ECB in  
EVENT-BLOCK (the exit finds the ECB by  
searching the TASK LIST TABLE by TCB  
addr)  
add timer ECB addr to WAIT list
2. RECEIVE events:  
serialize on mailbox  
find mailbox  
address of MAILBOX TABLE entry in

- EVENT-BLOCK  
address of mailbox storage in MAILBOX TABLE  
entry  
if any messages in mailbox,  
POST the ECB in the EVENT-BLOCK  
if EVENT-NUMBER is lowest of those completed  
save EVENT-NUMBER and address of  
EVENT-BLOCK  
else  
clear ECB  
add ECB address to WAIT list  
release use of mailbox
3. LAN RECEIVE events:  
check ECB in the EVENT-BLOCK  
if POSTed  
if EVENT-NUMBER is lowest of those  
completed  
save EVENT-NUMBER and address of  
EVENT-BLOCK  
else  
add ECB address to WAIT list
- D. IF NO EVENTS HAVE COMPLETED,  
WAIT ON THE LIST OF UNCOMPLETED EVENTS
1. WAIT on the list of ECB's until control is  
returned (at least one event has completed)
- E. OF THE EVENTS THAT HAVE COMPLETED,  
RETURN THE HIGHEST PRIORITY EVENT
1. Search the ECB list for completed events
2. If EVENT-NUMBER is lowest of those completed  
save EVENT-NUMBER and address of EVENT-BLOCK
3. Set caller's EVENT-NUMBER to that saved (highest  
priority)
4. If the returned event is a timer,  
re-initialize the EVENT-BLOCK (character 0's)  
clear TWA timer-related fields
- F. RETURN CONTROL TO CALLER
1. Set 'successful completion' STATUS-CODE

2. RETURN to caller

3.10 Log an Error Message

The ERRPRO primitive routine is in program OSIERR. This program can be called from an ICAM/IISS program directly or be LINKed to/from the IPC, PRC or IHC programs. It formats and time-stamps the error message and sends it to the mailbox for the Error Log Write task.

CALL 'ERRPRO' USING MESSAGE-NUMBER  
PROGRAM-NAME  
MESSAGE-TEXT.

FUNCTIONS PERFORMED:

- A. BUILD ERROR MESSAGE
  - 1. Concatenate parameters into one message
- B. SEND ERROR MESSAGE TO ERROR LOG WRITE TASK
  - 1. Send message to mailbox ERRMBX
  - 2. If any error, ignore it
- C. RETURN CONTROL TO CALLER
  - 1. RETURN to caller

3.11 Terminate Processing

The ENDRUN primitive routine is in program OSIIBM.

CALL 'ENDRUN'.

STATUS CODES:  
none (control is not returned)

FUNCTIONS PERFORMED:

- A. TERMINATE THE CALLER'S PROGRAM
  - 1. Restore the ATTACH stub's registers and RETURN

## SECTION 4

### PROCESS CONTROL PRIMITIVES (PRC)

#### 4.1 Create Process

The CRTPRC primitive routine is in program OSIPRC.

CALL 'CRTPRC' USING AP-NAME  
PROCESS-NAME  
PRIORITY  
TYPE-FLAG  
DIRTBL  
NTM-STATUS-CODE  
OPSY-RETCODE

#### FUNCTIONS PERFORMED:

##### A. VALIDATE PARAMETERS

1. If ap-name contains embedded blanks  
set 'invalid application name' in NTM-RETURN  
LINK to ERRPRO to log error  
RETURN to caller
2. If process-name contains embedded blanks  
set 'invalid process name' in NTM-RETURN  
LINK to ERRPRO to log error  
RETURN to caller
3. If type-flag not valid  
set 'invalid priority' in NTM-RETURN  
LINK to ERRPRO to log error  
RETURN to caller
4. If priority not valid \*not done now, NTM  
doesn't use it\*  
set 'invalid priority' in NTM-RETURN  
LINK to ERRPRO to log error  
RETURN to caller

##### B. CHECK FOR DUPLICATE PROCESS-NAME

1. Load address of COMMON TABLE from TWA  
(contains TASK LIST TABLE and PROGRAM  
RE-ROUTING TABLE)

2. Serialize on the TASK LIST TABLE by process-name
  3. Search TASK LIST TABLE by process-name
  4. If duplicate process-name  
set 'duplicate process name' in NTM-RETURN  
LINK to ERRPRO to log error  
release control of TASK LIST TABLE  
RETURN to caller
- C. DETERMINE IF REQUEST SHOULD BE RE-ROUTED
1. Search PROGRAM RE-ROUTING TABLE using ap-name  
length of compare is in table entry,  
so the search can be generic
- D. IF ENTRY FOUND, RE-ROUTE CREATE PROCESS REQUEST  
\*\*\* not implemented \*\*\*
1. Format create-process message:  
'CRTPRC PARMS@\_\_\_\_,ECB@\_\_\_\_'
  2. Release control of the TASK LIST TABLE
  3. Send message to mailbox specified in entry
  4. WAIT on RE-ROUTE ECB
  5. If POSTed RE-ROUTE ECB not zeros  
set 'create process failed' in NTM-RETURN  
LINK to ERRPRO to log error  
  
else  
  
set 'successful completion' in NTM-RETURN
  6. RETURN to caller
- E. IF ENTRY NOT FOUND, CREATE THE PROCESS
1. Search TASK LIST TABLE for an empty slot  
If not empty slot is found,  
GETMAIN additional storage, chain and  
format it  
LINK to ERRPRO to record the overflow

2. Format TASK LIST TABLE entry  
    move in process-name, ap-name, task  
        creation time  
    clear end-of-task ECB
3. Create the process  
    ATTACH EP=(ATTACH-STUB)  
    PARAM=(parameter list),  
        (passed to Create Process)  
    ECB=(END-OF-TASK ECB),  
        (in TASK LIST TABLE entry)  
    dispatching priority = -1, (default)  
    ETXR=(END-OF-TASK exit routine address)

F. RETURN TO CALLER

1. Set 'successful completion' in NTM-RETURN
2. Release control of the TASK LIST TABLE
3. RETURN to caller

4.2 Delete Process

The DELPRC primitive routine is in program OSIPRC.

CALL 'DELPRC' USING AP-NAME PROCESS-NAME  
                  NTM-STATUS-CODE  
                  OPSYS-RETCODE.

FUNCTIONS PERFORMED:

A. VALIDATE PARAMETERS

1. If process-name contains embedded blanks  
    set 'invalid process name' in NTM-RETURN  
    LINK to ERRPRO to log error  
    RETURN to caller

B. DETERMINE IF REQUEST SHOULD BE REROUTED

1. Load address of COMMON TABLE from TWA  
    (contains PROGRAM RE-ROUTING TABLE)
2. Search PROGRAM RE-ROUTING TABLE using process-name  
    \*\*\*note that this routine assumes that ap-name\*\*\*

\*\*\*is the same as the first part of  
process-name\*\*\*  
length of compare is in table entry,  
so the search can be generic

C. IF ENTRY FOUND, RE-ROUTE DELETE PROCESS REQUEST  
\*\*\* not implemeted \*\*\*

1. Format delete-process message:  
'DELPRC PARM@\_\_\_\_,ECB@\_\_\_\_'
2. Send message to mailbox specified in entry
3. WAIT on RE-ROUTE ECB not zeros
4. If POSTed RE-ROUTE ECB not zeros  
set 'delete process failed' in NTM-RETURN  
LINK to ERRPRO to log error  
  
else  
  
set 'successful completion' in NTM-RETURN
5. RETURN to caller

D. IF ENTRY NOT FOUND, DELETE THE PROCESS

1. Search TASK LIST TABLE for process-name
2. If process-name not found (the process has already ended)
3. Pick up TCB address of process (from TASK LIST TABLE entry)
4. Issue DETACH TCB=(TCB address)
5. LINK to the End-of-Task exit

E. RETURN TO CALLER

1. Set 'successful completion' in NTM-RETURN
2. RETURN to caller

4.3 Request Process Name

DS 620143300  
1 November 1985

The GETNAM primitive routine is in program OSIPRC.

CALL 'GETNAM' USING PROCESS-NAME  
RETURN CODE  
NTM-STATUS-CODE.

FUNCTIONS PERFORMED:

A. RETURN PROCESS-NAME

1. Pick up our process-name from TWA
2. Move it to PROCESS-NAME

B. RETURN TO CALLER

1. RETURN to caller

## SECTION 5

### PRC SUPPORT ROUTINES

#### 5.1 ATTACH Stub (Program OSIATCH)

Control will be passed to the ATTACH stub when any task is ATTACHED as a result of a Create Process request.

ATTACH 'ATTACH-Stub' PARAM=    AP-NAME  
                                  PROCESS-NAME  
                                  PRIORITY  
                                  TYPE-FLAG  
                                  NTM-STATUS-CODE  
                                  OPSYS-RETCODE.

#### FUNCTIONS PERFORMED:

##### A. OBTAIN TASK WORK AREA

1. GETMAIN Task Work Area (TWA) which consists of Register Save Areas (for OSIIBM and the ATTACH stub) and the Task Work Area for the primitives
2. Clear TWA and prime the TWA indicator field

##### B. PASS CONTROL TO THE APPLICATION PROGRAM

1. LINK to AP-NAME program passing  
    address of original parameter list in register  
    1  
    address of ATTACH Stub's Register Save Area  
    (in the TWA) in register 13
2. When control is returned, RETURN to caller (MVS)

#### 5.2 End-of-task Exit (Program OSIETXR)

Control will be passed to the ETXR routine by MVS when a subtask created by an ATTACH macro completes (normally or abnormally), or when DELPRC LINKs to it after DETACHing a subtask.

#### FUNCTIONS PERFORMED:

##### A. FIND AND CHECK THE TASK LIST TABLE ENTRY

DS 620143300  
1 November 1985

1. LOAD COMMON TABLE (contains the TASK LIST TABLE and the MAILBOX TABLE)
  2. Serialize on TASK LIST TABLE
  3. Search TASK LIST TABLE by TCB address
  4. Check return code or completion code in END-OF-TASK ECB in the TASK LIST TABLE entry
  5. If return code not zeros  
LINK to ERRPRO to log abend
- B. FIND AND REMOVE ANY TABLE ENTRIES
1. Serialize on MAILBOX TABLE
  2. Search MAILBOX TABLE by TCB address for mailbox(es) and remove table entries
  3. Release control of MAILBOX TABLE
  4. Remove TASK LIST TABLE
  5. Release control of TASK LIST TABLE
- C. REMOVE SUBTASK FROM SYSTEM
1. If subtask was not DETACHED by DELPRC,  
DETACH subtask
- D. RETURN TO CALLER
1. RETURN to caller (MVS)

## SECTION 6

### ENVIRONMENT CONTROL MODULES

#### 6.1 MVS Initialization (Program OSIMVSI)

This program is the first program executed when the region comes up (it is the program specified in the EXEC card of the JCL, or as the program to be executed under TSO TEST).

It LOADs the COMMON TABLE, and then searches the MODULE LOAD TABLE and LOADs any modules specified, and searches the TASK ATTACH TABLE and calls CRTPRC to ATTACH any tasks specified, and then searches the PROGRAM LINK TABLE and LINKs to any programs specified. One program that must be in the PROGRAM LINK TABLE is the NTM Monitor AP.

The reason this program issues LOADs of various modules, such as the END-OF-TASK EXIT routine and the VTAM CONTROL BLOCKS, is to insure that these modules are always in virtual storage by keeping their use counts non-zero.

The programs that are ATTACHed are various independent processes, such as the ERROR LOG WRITE task.

NOTE: Since this facility is table-driven, other modules or independent tasks could easily be added in the future --such as a task that submits a batch job when a Create Process request is re-routed to it. The section of this document on the COMMON TABLE contains a description of the tables that drive this program.

#### FUNCTIONS PERFORMED:

##### A. INITIALIZATION

1. GETMAIN Task Work Area (TWA) which consists of Register Save Areas (for OSIIBM and OSIMVSI) and the Task Work Area for the primitives
2. Clear TWA and prime the TWA indicator field
3. LOAD COMMON TABLE  
contains: MODULE LOAD TABLE  
TASK ATTACH TABLE  
PROGRAM LINK TABLE

## TASK LIST TABLE

### B. LOAD OTHER MODULES

#### 1. Search MODULE LOAD TABLE

NOTE: This table will contain such modules as:  
ETXR routine (end-of-task exit) VTAM Control  
Block Module(s)

2. For any entries found,  
LOAD 'module-name'

### C. ATTACH OTHER TASKS

#### 1. Search TASK ATTACH TABLE

NOTE: This table will contain such tasks as:  
Error Log Write Task

2. For any entries found,  
call CRTPRC to create the task, passing the  
parameter list in the table entry

### D. LINK TO OTHER PROGRAMS

#### 1. Search PROGRAM LINK TABLE

NOTE: This table will contain such programs as:  
NTM Monitor AP

2. For any entries found,  
LINK 'AP-program-name',  
PARAM=(param list)  
(same as in Create Process)

### E. RETURN TO CALLER

1. When control is returned to this program,  
(last program LINKed to having returned)  
RETURN to caller (MVS)  
(IISS system terminates)

## 6.2 Common Table

Description:

The COMMON TABLE is a load module generated from assembler macro calls, which is used to hold information required by all tasks in the system. The initial contents of this table will be set up by OSI but can easily be changed in the future if any changes are desired or new facilities are added.

NOTE: The COMMON TABLE must be link-edited as re-entrant, so that all tasks will reference the same copy of the table. To mark it re-entrant, add the RENT option to the PARM of the link-edit job step.

The COMMON TABLE actually consists of several tables:

1. MODULE LOAD TABLE
2. TASK ATTACH TABLE
3. PROGRAM LINK TABLE
4. MAILBOX TABLE TABLE
5. TASK LIST TABLE
6. PROGRAM RE-ROUTING TABLE

The first three tables are used by the MVS INITIALIZATION program to initialize the region before control is given to the NTM Monitor AP.

1. The MODULE LOAD TABLE contains entries for those load modules and subroutines which should be in virtual storage at all times. By issuing a LOAD for these modules, and then never deleting the modules, the use counts of the modules will always be above zero, thereby insuring that they will be kept in virtual storage.

Sample macro calls are:

```
COMTBL TYPE=LOAD,MODULE=OSIETXR  
COMTBL TYPE=LOAD,MODULE=xxxx (xxxx = VAX  
port-name)
```

2. The TASK ATTACH TABLE contains entries for those independent tasks that need to be started when the region is first brought up. For now, the only entry in this table will be for the Error Log Write Task, but

it might be desirable in the future to have a task which submitted a batch job when a Create Process request was re-routed to it.

Sample macrocalls are:

```
COMTBL TYPE=ATTACH,APNAME=ERLOG,PRNAME=ERLOG1,  
        PRIORITY=10,TYPEFLG=1  
COMTBL TYPE=ATTACH,APNAME=SUBMT,PRNAME=SUBMT1,  
        PRIORITY=20,TYPEFLG=1
```

A TYPE=ATTACH macro call will result in a table entry containing a parameter list used by OSIMVSI in a CRTPRC call to create the subtask requested.

3. The PROGRAM LINK TABLE contains entries for those programs which should be LINKed to by the MVS INITIALIZATION program. This list could include various initialization and termination programs as well as the NTM Monitor AP itself, although for now the NTM Monitor AP is the only entry.

Sample macro calls are:

```
COMTBL TYPE=LINK,APNAME=SETUP,PRNAME=SETUP1  
COMBTL TYPE=LINK,APNAME=NTMAP,PRNAME=NTMAP1  
COMBTL TYPE=LINK,APNAME=TRMNMT,PRNAME=TRMNT1
```

A TYPE=LINK macro call will result in a parameter list used in a LINK to the APNAME program issued by OSIMVSI, passing a parameter list, the same as that passed for Create Process.

4. The MAILBOX TABLE is used to identify and locate every mailbox in the system. An entry in this table is allocated when the mailbox is deleted.

An entry in this table consists of:

- the mailbox name,
- the address of the storage for the mailbox,
- the address of the TCB of the mailbox owner, and
- the address of the ECB to POST when a message is sent to the mailbox (in the EVENT-BLOCK).

The number of MAILBOX TABLE entries to allow for is determined by the expected activity of the system and

is specified as a parameter in the TYPE-INITIAL macro used to assemble the COMMON TABLE. Provision is made to allocate additional storage for table entries in case the table gets filled, and the number of additional entries is also specified in the macro.

A sample macro call is:

COMTBLE TYPE=INITIAL,MBXS=150,MBX=70

5. The TASK LIST TABLE is used to keep track of every task executing in the system. An entry in the table is allocated when a process is created and deleted when the task ends normally or is deleted by a Delete Process request.

An entry in this table consists of:

- the process name,
- the application name,
- the type flag,
- the address of the TCB for the task,
- an ECB that MVS POSTs when the task completes, and
- the task creation time.

The number of entries to allow for is specified as a parameter in the TYPE=INITIAL macro for the COMMON TABLE. As with the MAILBOX TABLE, provision is made to allocate additional storage for table entries in case the table gets filled, and the number of additional entries is also specified in the macro.

A sample macro call is:  
COMTBL TYPE=INITIAL,TSKS=100,TSKI=50

6. The PROGRAM RE-ROUTING TABLE could be used for two purposes:
  - a. To reroute Create Process requests to a task that causes the process to be started in another environment, such as to a task that submits batch jobs, and
  - b. To control the subtask hierarchy in the native VTAM region by re-routing a Create Process request to a task that will do the ATTACH on behalf of the caller, rather than attaching the subtask directly

DS 620143300  
1 November 1985

to the originating task.

The program name supplied can be the full program name, or a generic name, of the length implied. This would allow, for example, to re-route to batch all query processors beginning with QP.

A sample macro call is:

```
COMBTL TYPE=REROUTE,PROGRAM=COMPU,TO=MVSMBX  
COMBTL TYPE=REROUTE,PROGRAM=QP,TO=BTCHMBX
```

NOTE: The code will be put into the Create Process primitive to search this table and to be able to re-route the request, but for now no tasks will exist to accept the re-routed request, since neither of the above functions is currently planned for.

Sample source input to generate the COMMON TABLE looks like this:

```
COMBTL TYPE=INITIAL,MBXS=150,MABXI=70,TAKS=100,  
TSKI=50  
COMBTL TYPE=LOAD,MODULE=OSIETXR  
COMBTL TYPE=LOAD,MODULE=XXXX  
(XXXX = VAX port name)  
COMBTL TYPE=ATTACH,APNAME=ERLOG,PRNAME=ERLOG1  
PRIORITY=10,TYPEFLAG=1  
COMBTL TYPE=LINK,APNAME=NTMAP,PRNAME=NTMAP1  
COMBTL TYPE=REROUTE,PROGRAM=QP,TO=BTCHMBX  
COMBTL TYPE=FINAL
```

## SECTION 7

### INTER-HOST PRIMITIVES (IHC)

#### 7.1 Initialize Communication with the VAX or Honeywell Level 6

The INILAN primitive routine is in program OSIIHC.

```
CALL 'INILAN' USING PORT-NAME
                        RCV-BLOCK
                        XMIT-BLOCK
                        EVENT-BLOCK-nn
                        STATUS.
```

#### FUNCTIONS PERFORMED:

##### A. VALIDATE PARAMETERS

1. If PORT-NAME is invalid  
set a 'system-dependent error' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller
2. If EVENT-BLOCK is not all zeros  
set 'event block no initialized' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller

##### B. CHECK IF COMMUNICATION ALREADY ESTABLISHED

1. LOAD VTAM control block load module (name =  
PORT-NAME)
2. If already initialized  
(allow a second initialize to be issued)
  - a. CLSDST netname (obtained from VTAM c.b.  
module)

##### C. PRIME CONTROL BLOCKS

1. Move zeros to RCV-BLOCK and XMIT-BLOCK
2. Move PORT-NAME to RCV-BLOCK and XMIT-BLOCK
3. Move PORT-NAME to EVENT-BLOCK and TWA

4. Set address of EVENT-BLOCK in TWA

D. ESTABLISH CONTROL OF PORT-NAME

1. OPEN ACB for this APPLID  
OPNDST netname
2. If any error  
set a 'system-dependent error' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller

E. RETURN TO CALLER

1. Set 'successful completion' STATUS-CODE
2. RETURN to caller

7.2 Transmit a Message to the VAX or Honeywell Level 6

The XMTLAN primitive routine is in program OSIIHC.

CALL 'XMTLAN' USING XMIT-BLOCK  
EVENT-BLOCK-nn  
STATUS.

FUNCTIONS PERFORMED:

A. VALIDATE PARAMETERS

1. If number-of-bytes is zero  
set 'number of bytes zero' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller
2. If number-of-bytes is not numeric or is  
greater than the max  
set 'number of bytes greater than maximum'  
STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller

B. CHECK EVENT-BLOCK AND OTHER CONTROL BLOCKS

1. If PORT-NAME (in TWA) not in XMIT-BLOCK and  
EVENT-BLOCK  
set 'invalid event block for LAN'

STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller

2. If receive is outstanding (EVENT-OUTSTANDING is 01)  
set 'receive from LAN is outstanding'  
STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller

C. TRANSMIT THE MESSAGE

1. SEND the message
2. If any error,  
set a 'system-dependent error' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller

D. RETURN CONTROL TO CALLER

1. Set 'successful completion' STATUS-CODE
2. RETURN to caller

7.3 Receive a Message from the VAX or Honeywell Level 6

The RCVLAN primitive routine is in program osiihc.

CALL 'RCVLAN' USING RCV-BLOCK  
EVENT-NUMBER  
EVENT-BLOCK-NN  
STATUS.

FUNCTIONS PERFORMED:

A. VALIDATE PARAMETERS

1. If buffer-size is zero  
set 'buffer size zero' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller
2. If buffer-size is not numeric or is greater than max  
set 'buffer size greater than maximum'

DS 620143300  
1 November 1985

STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller

3. If event-number is zero  
set 'event number zero' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller
4. If event-number is not numeric or is greater  
than max  
set 'event-number greater than maximum'  
STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller

B. CHECK EVENT-BLOCK AND OTHER CONTROL BLOCKS

1. If PORT-NAME (in TWA) not in RCV-BLOCK and  
EVENT-BLOCK  
set 'invalid event block for LAN' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller
2. If RECEIVE is outstanding already  
(EVENT-OUTSTANDING is 01)  
set 'only one outstanding receive permitted'  
STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller
3. If previous RECEIVE was returned  
(EVENT-OUTSTANDING is 02)  
set OUTSTANDING-EVENT to 00  
Clear ECB (COMM doesn't want data)

C. PRIME EVENT-BLOCK AND OTHER REQUIRED AREAS

1. Set EVENT-TYPE = 03  
EVENT-NUMBER = event-number  
OUTSTANDING-EVENT = 01  
address of buffer, buffer length

D. ISSUE RECEIVE

1. RECEIVE, asynchronous

2. If any error  
set a 'system-dependent error' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller

E. RETURN CONTROL TO CALLER

1. Set 'successful completion' STATUS-CODE
2. RETURN to caller

7.4 Get a Message from the VAX or Honeywell Level 6

The GETLAN primitive routine is in program OSIHC.

CALL 'GETLAN' USING RCV-BLOCK  
EVENT-BLOCK-nn  
STATUS.

FUNCTIONS PERFORMED:

A. VALIDATE PARAMETERS

1. If buffer size is zero  
set 'buffer size zero' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller
2. If buffer-size is not numeric or is greater  
than max  
set 'buffer size greater than maximum'  
STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller

B. CHECK EVENT-BLOCK

1. If PORT-NAME (in TWA) not in RCV-BLOCK and  
EVENT-BLOCK  
set 'invalid event block for LAN' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller
2. If EVENT-TYPE is not RECEIVE from LAN (03)  
set 'not a receive terminal block' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller

3. If no RECEIVE from LAN is outstanding  
(EVENT-OUTSTANDING = 00)  
set 'no receive outstanding' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller

C. GET MESSAGE FROM TERMINAL

1. If ECB (in EVENT-BLOCK) is not POSTed (by VTAM)  
set 'receive not satisfied' STATUS-CODE  
RETURN
2. If data length exceeds buffer-size  
set 'buffer too small' STATUS-CODE  
(data is lost)  
LINK to ERRPRO to log error  
  
else  
  
move data to buffer  
set NUMBER-OF-BYTES  
set 'successful completion' STATUS-CODE

D. CLEAR OUTSTANDING RECEIVE FROM LAN

1. Set OUTSTANDING-EVENT to 00
2. Clear ECB

E. RETURN CONTROL TO CALLER

1. RETURN to caller

7.5 Cancel a Receive from the VAX or Honeywell Level 6

The CNLLAN primitive routine is in program OSIHC.

CALL 'CNLLAN' USING RCV-BLOCK  
EVENT-BLOCK-nn  
STATUS.

FUNCTIONS PERFORMED:

- A. CHECK EVENT-BLOCK

1. If PORT-NAME (in TWA) not in RCV-BLOCK and  
EVENT-BLOCK  
set 'invalid event block for LAN' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller
  2. If EVENT-TYPE not a RECEIVE from LAN  
(EVENT-TYPE = 03)  
set 'not a receive terminal block' STATUS CODE  
LINK to ERRPRO to log error  
RETURN to caller
  3. If no RECEIVE from LAN is outstanding  
set 'no receive outstanding' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller
- B. CANCEL RECIEVE FROM LAN
1. CANCEL RECEIVE
  2. Set OUTSTANDING-EVENT to 00
  3. Clear ECB (COMM doesn't want data)
- C. RETURN CONTROL TO CALLER
1. Set 'successful completion' STATUS-CODE
  2. RETURN to caller

#### 7.6 Terminate Communication with the VAX or Honeywell Level 6

The TRMLAN primitive routine is in program OSIHC.

CALL 'TRMLAN' USING PORT-NAME  
RCV-BLOCK  
XMIT-BLOCK  
EVENT-BLOCK-nn  
STATUS.

#### FUNCTIONS PERFORMED:

##### A. VALIDATE PARAMETERS

1. If PORT-NAME is invalid  
set a 'system-dependent error' STATUS-CODE

DS 620143300  
1 November 1985

LINK to ERRPRO to log error  
RETURN to caller

B. CLEAR CONTROL BLOCKS

1. Move zeros to RCV-BLOCK and XMIT-BLOCK
2. Move zeros to EVENT-BLOCK
3. Clear TWA fields

C. TERMINATE CONTROL OF PORT-NAME

1. CLSDST netname  
CLOSE ACB for this APPLID
2. If any error  
set a 'system-dependent error' STATUS-CODE  
LINK to ERRPRO to log error  
RETURN to caller

D. RETURN CONTROL TO CALLER

1. Set 'successful completion' STATUS-CODE
2. RETURN to caller

## SECTION 8

### INTERFACE TO CICS APPLICATION

The support for a CICS application such as PIOS is handled by the following software:

1. A Pseudo-AP, which runs as an MVS subtask in the same region as the NTM, and acts like an integrated AP. It calls the VTI to convert data streams to and from 3270 format and also calls the CICS interface to send those data streams to CICS and receive data back from CICS.
2. OSICICS, the interface to CICS, which is the only layer of this software which knows it is dealing with CICS. It is called by the Pseudo-AP to send and receive data streams to and from CICS. It in turn branches to the 3270 emulator program to perform the actual communication with CICS.

It also generates some messages for CICS, such as a CICS sign-on message, and sign-off message and interprets the output from CICS as to whether or not the requested function has completed successfully.

3. OSI3270, a 3270 emulator program in native VTAM, which logs on to CICS, and sends and receives data to and from CICS as if it were a 3270. This program does not know it is dealing with CICS but merely handles the data transfer to whatever VTAM application it is in communication with.
4. A remote CICS, running the CICS application (PIOS).

#### 8.1 Pseudo-AP

The Pseudo-AP is started by the NTM MPU for the PIOS AP cluster. It is called a Pseudo-AP because it is not the real application. It performs the following functions:

##### A. INITIALIZE

1. CALL 'INITAL' (NTM service) to create input mailbox
2. CALL 'GETUSR' (NTM service) to obtain user id

DS 620143300  
1 November 1985

3. CALL 'INICIS' (CICS interface) USING USER-ID  
BUFFER  
BUFFER-LENGTH  
EVENT-BLOCK-C  
STATUS-CICS.

Note: Data returned in the buffer will consist of a data stream to clear the screen.

B. SEND MESSAGE TO TERMINAL OPERATOR AND RECEIVE RESPONSE

1. CALL 'VTI???' (VTI 3270 to neutral) USING BUFFER  
BUFFER-LENGTH  
NUMBER-OF-BYTES  
STATUS-VTI.

Note: Buffer and number-of-bytes will be modified to contain the neutral format data stream to be sent to the terminal and its length.

2. CALL 'OIVTI' (VTI output/input) USING BUFFER  
BUFFER-LENGTH  
NUMBER-OF-BYTES  
STATUS-VTI.

Note: The VTI will send the neutral data stream to the terminal attached to the VAX and wait for input from the operator. When control is returned to this program, the buffer and number-of-bytes will be modified to contain the neutral format data stream received back from the terminal and its length.

3. When response is received from operator.

CALL 'VTI???' (VTI neutral to 3270) USING BUFFER  
BUFFER-LENGTH  
NUMBER-OF-BYTES  
STATUS-VTI.

Note: Buffer and number-of-bytes will be modified to contain the 3270 format data stream to send to CICS and its length

C. END PROCESS IF OPERATOR INDICATES TO

1. IF ATTENTION-KEY (equivalent of the break key in the VAX) has been struck:
  - a. Issue a call to OSICICS to terminate:  
CALL 'TRMCIS' USING EVENT-BLOCK-C  
STATUS-CICS.
  - b. Format a session terminate message for the operator
  - c. Convert the data stream to neutral  
CALL 'VTI???' USING BUFFER  
BUFFER-LENGTH  
NUMBER-OF-BYTES  
STATUS-VTI.
  - d. Send to operator with no response  
CALL 'OTVTI' USING BUFFER  
BUFFER-LENGTH  
NUMBER-OF-BYTES  
STATUS-VTI.
  - e. Terminate process  
CALL 'TRMNAT' (NTM service) using...  
(process terminates)

D. SEND OPERATOR INPUT TO CICS AND RECEIVE RESPONSE

1. CALL 'SNDICIS' (CICS interface) USING BUFFER  
NUMBER-OF-BYTES  
EVENT-BLOCK-C  
STATUS-CICS.  
  
Note: Data will be sent to CICS
2. CALL 'RCVCIS' (CICS interface) USING BUFFER  
BUFFER-LENGTH  
NUMBER-OF-BYTES  
EVENT-BLOCK-C  
STATUS-CICS.
3. CALL 'GETCIS' (CICS interface) USING BUFFER  
BUFFER-LENGTH  
NUMBER OF BYTES  
EVENT-BLOCK-C  
STATUS-CICS.

4. If receive is satisfied, branch to step B.1.

E. TERMINATE PROCESS IF SESSION IS LOST

1. If receive is not satisfied,

a. Set timer

CALL 'SETTIM' USING TIME-INTERVAL  
EVENT-NUMBER  
EVENT-BLOCK-T  
EVENT-BLOCK-C  
STATUS-CODE.

b. WAIT for receive or timer to complete

CALL 'WAIT02' USING EVENT-NUMBER  
STATUS-CODE  
NUMBER-OF-EVENT-BLOCKS  
EVENT-BLOCK-T.

2. If EVENT-NUMBER indicates timer expired,

a. Cancel outstanding RECEIVE

CALL 'CNLCIS' USING EVENT-BLOCK-C  
STATUS-CICS.

b. Terminate 3270 emulation

CALL 'TRMCIS' USING BUFFER  
BUFFER-LENGTH  
EVENT-BLOCK-C  
STATUS-CICS.

c. Format termination message for terminal operator

d. Send message to operator with no response

CALL 'VTI???' (VTI 3270 to neutral) USING BUFFER  
BUFFER-LENGTH  
NUMBER-OF-BYTES  
STATUS-VTI

CALL 'OTVTI' (VTI output) USING BUFFER  
BUFFER-LENGTH  
NUMBER-OF-BYTES  
STATUS-VTI.

e. Terminate

CALL 'TRMNAT' (NTM service) using...  
(process terminates)

DS 620143300  
1 November 1985

3. If EVENT-NUMBER indicates receive was satisfied,  
CALL 'GETCIS' (CICS interface) USING BUFFER  
BUFFER-LENGTH  
NUMBER-OF-BYTES  
EVENT-BLOCK-C  
STATUS-CICS.
4. Branch to step B.1.

SECTION 9

CICS INTERFACE PRIMITIVES

9.1 Initialize Communication with CICS

CALL 'INICIS' USING USER-ID  
BUFFER  
BUFFER-LENGTH  
EVENT-BLOCK  
STATUS-CICS.

FUNCTIONS PERFORMED:

A. VALIDATE PARAMETERS

1. If parameter list is invalid  
set 'invalid parameter list specified' STATUS-CICS  
Branch to ERRPRO to log the error  
RETURN to caller
2. If user-id is blanks or zeros  
set 'invalid user id' STATUS-CICS  
Branch to ERRPRO to log the error  
RETURN to caller
3. If buffer-length is zeros  
set 'buffer length zero' STATUS-CICS  
Branch to ERRPRO to log the error  
RETURN to caller
4. If buffer-length is non-numeric or is greater than  
max  
set 'buffer length exceeds maximum' STATUS-CICS  
Branch to ERRPRO to log the error  
RETURN to caller

B. LOG ON TO CICS

1. Prime EVENT-BLOCK for INITIALIZE:  
action code for initialize
2. Branch to OSI3270, passing the EVENT-BLOCK
3. If status indicates no session is available  
set 'retry later' STATUS-CICS

Branch to ERRPRO to log the error  
RETURN to caller

4. If status indicates a VTAM error  
set 'system-dependent error' STATUS-CICS  
Branch to ERRPRO to log the error  
RETURN to caller

C. SIGN ON TO CICS

1. Build the SIGN-ON message for CICS in the caller's  
buffer using the user-id that was passed
2. Prime EVENT-BLOCK for SEND:  
action code for send  
address of data  
length of data
3. Branch to OSI3270, passing the EVENT-BLOCK
4. If status indicates a VTAM error  
set 'system-dependent error' STATUS-CICS  
Branch to ERRPRO to log the error  
RETURN to caller

D. RECEIVE RESPONSE FROM CICS TO SIGN ON

1. Prime EVENT-BLOCK for RECEIVE:  
action code for receive  
address of buffer  
length of buffer
2. Branch to OSI3270, passing the EVENT-BLOCK
3. If status indicates a VTAM error  
set 'system-dependent error' STATUS-CICS  
Branch to ERRPRO to log the error  
RETURN to caller
4. Prime EVENT-BLOCK for GET:  
action code for get  
address of buffer  
length of buffer
5. Branch to OSI3270, passing the EVENT-BLOCK
6. If RECEIVE is not satisfied

set a timer and wait on the timer and the receive  
RETURN to caller  
(caller should issue a wait followed by another  
GET)

7. If the timer expired,  
prime EVENT-BLOCK for TERMINATION  
branch to OSI3270 to terminate communication  
set 'initialization failed' STATUS-CICS  
branch to ERRPRO to log the error  
RETURN to caller
8. If the sign on was rejected (look at msg from  
CICS)  
prime EVENT-BLOCK for TERMINATION  
branch to OSI3270 to terminate communication  
set 'initialization failed' STATUS-CICS  
branch to ERRPRO to log the error  
RETURN to caller

Note: The response sent by CICS to the SIGN-ON is  
discarded.

#### E. FORMAT RESPONSE FOR OPERATOR

1. Build a CLEAR SCREEN data stream in the caller's  
buffer ERASE WRITE, FREE KEYBOARD, NO DATA
2. Set NUMBER-OF-BYTES to the length of the data  
stream

#### F. RETURN CONTROL TO CALLER

1. Set a 'successful completion'
2. RETURN to caller

#### 9.2 Send Message to CICS

CALL 'SNDICIS' USING BUFFER  
NUMBER-OF-BYTES  
EVENT-BLOCK  
STATUS-CICS.

#### FUNCTIONS PERFORMED:

##### A. VALIDATE PARAMETERS

1. If parameter list is invalid  
set 'invalid parameter list specified' STATUS-CICS  
Branch to ERRPRO to log the error  
RETURN to caller
2. If number-of-bytes is zeros  
set 'number of bytes zero' STATUS-CICS  
Branch to ERRPRO to log the error  
RETURN to caller
3. If number-of-bytes is non-numeric or is greater  
than max  
set 'number of bytes exceeds maximum' STATUS-CICS  
Branch to ERRPRO to log the error  
RETURN to caller

B. SEND MESSAGE TO CICS

1. Prime EVENT-BLOCK for SEND:  
action code for send  
address of data  
length of data
2. Branch to OSI3270, passing the EVENT-BLOCK

C. CHECK RESPONSE

1. If status indicates a VTAM error  
set 'system-dependent error' STATUS-CICS  
Branch to ERRPRO to log the error  
RETURN to caller

D. RETURN CONTROL TO CALLER

1. Set 'successful completion' STATUS-CICS
2. RETURN to caller

9.3 Receive a Message from CICS

CALL 'RCVCIS' USING BUFFER  
BUFFER-LENGTH  
NUMBER-OF-BYTES  
EVENT-BLOCK  
STATUS-CICS.

**FUNCTIONS PERFORMED:**

**A. VALIDATE PARAMETERS**

1. If parameter list is invalid  
set 'invalid parameter list specified' STATUS-CICS  
Branch to ERRPRO to log the error  
RETURN to caller
2. If buffer-length is zeros  
set 'buffer length zero' STATUS-CICS  
Branch to ERRPRO to log the error  
RETURN to caller
3. If buffer-length is non-numeric or is greater than  
max  
set 'buffer length exceeds maximum' STATUS-CICS  
Branch to ERRPRO to log the error  
RETURN to caller

**B. RECEIVE MESSAGE FROM CICS**

1. Prime the EVENT-BLOCK for a RECEIVE:  
action code for receive  
address of buffer  
length of buffer
2. Branch to OSI3270, passing the EVENT-BLOCK

**C. CHECK RESPONSE**

1. If status indicates a VTAM error  
set 'system-dependent error' STATUS-CICS  
Branch to ERRPRO to log the error  
RETURN to caller

**D. RETURN CONTROL TO CALLER**

1. Set 'successful completion' STATUS-CICS
2. RETURN to caller

**9.4 Get a Message from CICS**

CALL 'GETCIS' USING BUFFER  
BUFFER-LENGTH  
NUMBER-OF-BYTES

EVENT-BLOCK  
STATUS-CICS.

FUNCTIONS PERFORMED:

A. VALIDATE PARAMETERS

1. If parameter list is invalid  
set 'invalid parameter list specified' STATUS-CICS  
Branch to ERRPRO to log the error  
RETURN to caller
2. If buffer-length is zeros  
set 'buffer length zero' STATUS-CICS  
Branch to ERRPRO to log the error  
RETURN to caller
3. If buffer-length is non-numeric or is greater than  
max  
set 'buffer length exceeds maximum' STATUS-CICS  
Branch to ERRPRO to log the error  
RETURN to caller

B. GET MESSAGE FROM CICS

1. Prime EVENT-BLOCK for GET:  
action code for get  
address of buffer  
length of buffer
2. Branch to OSI3270, passing the EVENT-BLOCK

C. CHECK RESPONSE

1. If status indicates a VTAM error  
set 'system-dependent error' STATUS-CICS  
Branch to ERRPRO to log the error  
RETURN to caller
2. If receive is not satisfied  
set 'receive not satisfied' in STATUS-CICS  
Branch to ERRPRO to log the error  
RETURN to caller
3. Set NUMBER-OF-BYTES to length of message from CICS

D. RETURN CONTROL TO CALLER

1. Set 'successful completion' STATUS-CICS
2. RETURN to caller

#### 9.5 Cancel Receive from CICS

CALL 'CNLCIS' USING EVENT-BLOCK  
STATUS-CICS.

##### FUNCTIONS PERFORMED:

###### A. VALIDATE PARAMETERS

1. If parameter list is invalid  
set 'invalid parameter list specified' STATUS-CICS  
Branch to ERRPRO to log the error  
RETURN to caller

###### B. CANCEL RECEIVE

1. Prime EVENT-BLOCK for a CANCEL:  
action code for cancel
2. Branch to OSI3270, passing the EVENT-BLOCK

###### C. CHECK RESPONSE

1. If status indicates a VTAM error  
set 'system-dependent error' STATUS-CICS  
Branch to ERRPRO to log the error  
RETURN to caller

###### D. RETURN CONTROL TO CALLER

1. Set 'successful completion' STATUS-CICS
2. RETURN to caller

#### 9.6 Terminate Communication with CICS

CALL 'TRMCIS' USING BUFFER  
BUFFER-LENGTH  
EVENT-BLOCK  
STATUS-CICS.

##### FUNCTIONS PERFORMED:

A. VALIDATE PARAMETERS

1. If number of parameters is fewer than two  
set 'invalid parameter list specified' STATUS-CICS  
Branch to ERRPRO to log the error  
RETURN to caller

B. SIGN OFF CICS

1. Build the SIGN-OFF message for CICS in the caller's buffer
2. Prime EVENT-BLOCK for a SEND:  
action code for send  
address of data  
length of buffer
3. Branch OSI3270, passing the EVENT-BLOCK
4. If status indicates a VTAM error  
set 'system-dependent error' STATUS-CICS  
branch to ERRPRO to log the error  
branch to LOG OFF CICS
5. Prime EVENT-BLOCK for a RECEIVE:  
action code for receive  
address of buffer  
length of buffer
6. Branch to OSI3270, passing the EVENT-BLOCK
7. If status indicates a VTAM error  
set 'system-dependent error' STATUS-CICS  
branch to ERRPRO to log the error  
branch to LOG OFF CICS
8. Prime EVENT-BLOCK for GET:  
action code for get  
address of buffer  
length of buffer
9. Branch to OSI3270, passing the EVENT-BLOCK
10. If RECEIVE has not completed  
branch to LOG OFF CICS

Note: The response sent by CICS to the SIGN-OFF  
is discarded.

C. LOG OFF CICS AND VTAM

1. Prime EVENT-BLOCK for a TERMINATE:  
action code for terminate
2. Branch to OSI3270, passing the EVENT-BLOCK

D. CHECK RESPONSE

1. If status indicates a VTAM error  
set system-dependent error' STATUS-CICS  
Branch to ERRPRO to log the error  
RETURN to caller

E. RETURN CONTROL TO CALLER

1. Set 'successful completion' STATUS-CICS
2. RETURN to caller

## SECTION 10

### 3270 EMULATOR PROGRAM

The 3270 emulator program is designed to appear to the CICS as a local 3277 type terminal. All data flow control requests are handled by VTAM. The normal flow send/receive mode is full duplex. FM profile 2 and TS profile 2 are used.

The emulator program is linked to by OSICICS, which has determined which function the 3270 emulator is to perform and has placed the required parameters and the appropriate action code in the EVENT-BLOCK. The address of the EVENT-BLOCK is passed via a parameter list (with only one parameter) in register 1 to OSI3270.

#### FUNCTIONS PERFORMED:

##### A. INITIAL LOGON TO CICS

1. LOAD VTAM SLU TABLE and search for an available entry
2. If no entry is available,  
set 'no SLU control blocks available' in  
EVENT-BLOCK  
RETURN to caller  
else mark the SLU TABLE entry in use
3. OPEN VTAM ACB
4. If OPEN failed,  
release use of SLU TABLE entry in use  
set 'system dependent error' in EVENT-BLOCK  
RETURN to caller
5. Issue a SETLOGON - this macro must be issued  
before the 3270 emulator can request a session  
(VTAM restriction)
6. If register 15 is not zero  
set 'system dependent error' in EVENT-BLOCK  
move return code and feed back fields into  
EVENT-BLOCK  
RETURN to caller

7. Issue a REQSESS - this macro must specify the applid of the application that the 3270 emulator wishes to access
  8. If register 15 is not zero  
set 'system dependent error' in EVENT-BLOCK  
move return code and feed back fields into  
EVENT-BLOCK  
RETURN to caller
  9. A WAIT is then issued which will be posted when the SCIP exit gets control as a result of CICS responding to the REQSESS which was issued previously
  10. The SCIP exit performs the following functions:
    - a. If a BIND has flowed from CICS
      1. Issue an OPNSEC which acts as a positive response to the BIND
      2. If register 15 is not zero  
set 'system dependent error' in EVENT-BLOCK  
move return code and feed back fields into  
EVENT-BLOCK  
RETURN to caller
      3. POST ECB which is being waited on so the mainline program can continue processing
    - b. If an UNBIND has flowed from CICS, POST the ECB which the TERMSESS is waiting on
  11. Set 'successful completion' in EVENT-BLOCK
  12. RETURN to caller
- B. SEND TO CICS
1. Issue an asynchronous SEND to CICS
  2. WAIT on ECB to be POSTED by VTAM signaling completion of operation
  3. If register 15 is not zero  
set 'system dependent error' in EVENT-BLOCK  
move return code and feedback fields into

EVENT-BLOCK  
RETURN to caller

4. Set 'successful completion' in EVENT-BLOCK
5. RETURN to caller

C. RECEIVE from CICS

1. Issue an asynchronous RECEIVE from CICS
2. If register 15 is not zero  
set 'system dependent error' in EVENT-BLOCK  
move return code and feed back fields into  
EVENT-BLOCK  
RETURN to caller
3. Set 'successful completion' in EVENT-BLOCK
4. RETURN to caller

D. GET data from CICS

1. If RECEIVE ECB has not been posted  
set 'receive not satisfied' in EVENT-BLOCK  
RETURN to caller
2. Clear RECEIVE ECB
3. Set 'successful completion' in EVENT-BLOCK
4. RETURN to caller

E. CANCEL an outstanding RECEIVE

1. Issue a RESETSR to cancel outstanding RECEIVE
2. If register 15 is not zero  
set 'system dependent error' in EVENT-BLOCK  
move return code and feed back fields into  
EVENT-BLOCK  
RETURN to caller
3. Clear RECEIVE ECB
4. Set 'successful completion' in EVENT-BLOCK

5. RETURN to caller

F. TERMINATE session with CICS

1. Issue a TERMSESS to terminate session with CICS
2. WAIT on TERMSESS ECB which will be POSTED by SCIP  
exit
3. If register 15 is not zero  
set 'system dependent error' in EVENT-BLOCK  
move return code and feed back fields into  
EVENT-BLOCK  
RETURN to caller
4. CLOSE VTAM ACB
5. If register 15 is not zero  
set 'system dependent error' in EVENT-BLOCK  
move return code and feed back fields into  
EVENT-BLOCK  
RETURN to caller
6. Set 'successful completion' in EVENT-BLOCK
7. RETURN to caller

APPENDIX A  
MAILBOX LOGIC

**BUFFER WRAPAROUND**

The algorithm being used for mailboxes uses little cpu time for data movement but is rather complex. A mailbox is a fixed amount of storage, like a buffer, with messages being written to and read from it concurrently. The mailbox routine must keep track of where the first message to be read is and also where to write the next message sent to the mailbox. The problem is complicated by the fact that the messages are variable-length.

The routine keeps adding messages after the messages already in the mailbox until a message being sent doesn't fit. At this point, a check is made to see if the message will fit at the beginning of the mailbox. This will only happen if enough messages have already been read from the mailbox. If the message fits, it is put there, resulting in message sending having wrapped around.

Message reading also wraps around. When a message is to be read, but the spot where it is to be read from points beyond where any data has been put, message reading wraps around to the beginning of the mailbox buffer.

The storage in the mailbox can get fragmented using this technique. A message can be rejected even though there is enough space, because the space is not contiguous, due to the effects of wrapping around.

**FUNCTIONS PERFORMED:**

**A. Sending a Message**

```
If current-bytes = zero
set remove-displacement to zero
set insert-displacement to zero
set high-water-mark-displacement to zero
if msg-length <= mbx-size
    move message to buffer + 0
    add msg-length to insert-displacement
    add msg-length to current-bytes
    set high-water-mark-displacement to
        insert-displacement
```

```
else
    return 'msg too long' error

If insert-displacement > remove-displacement
    If insert-displacement + msg-length <= mbx-size
        move message to (buffer + insert-displacement)
        add msg-length to current-bytes
        set high-water-mark-displacement to
            insert-displacement
    else
        if msg-length <= remove-displacement
            move message to (buffer + 0)
            set insert-displacement to msg-length
        else
            return mbx full error

If insert-displacement < remove-displacement
    if msg-length <= (remove-displacement -
        insert-displacement)
        move message to (buffer + insert-displacement)
        add msg-length to insert-displacement
        add msg-length to current-bytes
    else
        return mbx full error

If insert-displacement = remove-displacement
    and current-bytes not = zero
        return mbx full error

B Getting a Message

If current bytes not = zero
    if remove-displacement not equal high-water-mark
        move msg (buffer + remove-displacement) to
            caller's buffer
        add msg length to remove displacement
    else
        move message (buffer + 0) to caller's buffer
        set remove displacement to msg length
        set high water mark to insert displacement
else
    return receive not satisfied error
```

rd = remove displacement, id = insert displacement




Figure 1. Simple case, no wraparound




Figure 2. Mailbox full




Figure 3. Condition for buffer wraparound on send




Figure 4. Mailbox full (due to fragmentation)





Figure 5. Condition for buffer wraparound on read

## APPENDIX B

## MODULE STRUCTURE CHART



13	+-----+	14	+-----+	15	+-----+	16	+-----+	17	+-----+
	COMMON		VTAM CB		VTAM CB		VTAM CB		VTAM SLU
	TABLE		VAX		HL6		CON		TABLE
	+-----+		+-----+		+-----+		+-----+		+-----+

\* These LINKS are to be replaced with direct branches.

#### MODULES:


1. The ATTACH STUB which GETMAINS and initializes the TWA
2. The COBOL program, such as COMM01 or COMM02, the NTM Monitor, the NTM MPUs, the Query Processors, or the Pseudo-APs
3. OSIIBM, which records the type of call and links to the appropriate interface routine (IPC, PRC, IHC, etc.)
4. IPC, the Inter-Process Primitives interface program
5. PRC, the Process Control Primitives interface program
6. IHC, the Inter-Host Primitives interface program
7. CON, the Console Primitives interface program
8. The CICS Interface, which allows the Pseudo-AP to talk to CICS
9. The 3270 Emulator, which emulates a local 3270 through VTAM
10. ETXR, the End-of-Task exit
11. ERRPRO, which can be linked to by the COBOL program or by any interface program, and formats and sends error messages
12. IHCEXT, the VTAM error exits for IHC
13. The COMMON TABLE, a load module which contains data required to run the IISS Test Bed on IBM
- 14, 15, 16. VTAM control block load modules for the VAX, the Honeywell Level 6, and the NTM console
17. The VTAM SLU table, which contains multiple sets of VTAM

control blocks to use to emulate 3270s into CICS

**NOTES:**

1. The ATTACH STUB is the first module to get control when a task is created
2. The ATTACH STUB LINKs to the COBOL program
3. CALL statements issued by the COBOL program are resolved by entry points in OSIIBM
4. OSIIBM LINKs to the appropriate interface routine to perform the requested function
5. The interface programs use data and control blocks contained in other load modules such as the Common Table, which are LOAded at system utilization

PROCESSING FLOW



DS 620143300  
1 November 1985

PROCESSING FLOW (Continued)

```
| +-----+  
| LINK *  
|  
|   ERRPRO (R1 =, ERRPRO parmlist (in TWA))  
+--> +-----+  
|   format error message  
|   send message to mailbox ERRMBX  
|   RETURN  
+-----+
```

DS 620143300  
1 November 1985

# SYSTEM INITIALIZATION

## MVS INITIALIZATION

MVS INITIALIZATION		TWA	
+--	GETMAIN TWA	+--	RSA for MVS INIT
	establish RSA (in TWA)		RSA for OSIIBM
	store A(TWA) in TWA		RSAs for IPC, PRC, IHC,
	LOAD COMMON TABLE		etc.
	store A(COMMON TABLE) in		A(TWA)
	TWA		A(COMMON TABLE)
	build own TASKLIST TABLE		
	entry		
	LOAD modules in MODULE		
	TABLE & save addrs in		
+--	MODULE TABLE: IPC, PRC,	+--	COMMON TABLE
	IHC, CON, ERRPRO, CICS		
	Interface, 3270 Emulator,		MODULE LOAD TABLE
	VTAM PLU control blocks,		TASK ATTACH TABLE
	VTAM SLU control block		PROGRAM LINK TABLE
	table		
	ATTACH tasks in ATTACH		MAILBOX TABLE
	TABLE using the CRTPRC		TASKLIST TABLE
	primitive: ERROR LOG		
	WRITE task		
+--	LINK to programs in LINK	+--	ATTACH STUB
	TABLE (e.g., the NTM		
	Monitor AP)		GETMAIN TWA, etc.
	RETURN (region terminates)		LINK to ERROR LOG
			WRITE
	OSIIBM		
+--		+--	LINK
			ERROR LOG WRITE task
			CALL 'CRTMBX' USING
			'ERRMBX'
			SIZE ...
			CALL 'WAIT01' USING
			MBX ...
+--	NTM Monitor AP (R1 =, CRTPRC parms)	+--	
+--	CALL 'CRTPRC' USING MON-MPU	+--	OSIIBM
	PRIORITY		
	STATUS.		

DS 620143300  
1 November 1985

```
+-----+
| OSIIBM(linked with COBOL pgm|
| .                               |
+-->| ENTRY CRTPRC                |
| search thru RSAs to find TWA|
| set type of call in TWA    |
| store A(CRTPRC parms) in TWA|
+-->| LINK to PRC program          |
| RETURN to COBOL pgm        |
+-----+
LINK *
```

```
PRC (R1 => A(TWA))
+-----+
| load A(TWA)                  |
| establish PRC RSA in TWA     |
| load A(COMMON TABLE)from TWA|
| a call to create a process? |
| .                             |
| CRTPRC RTN:                  |
| load A(parmlist) from TWA    |
| search TASKLIST TABLE      |
| if no duplicate,            |
| build TASKLIST TABLE entry.|
| ATTACH task                  |
| RETURN                      |
+-----+
```

```
ATTACH STUB
+-----+
| GETMAIN TWA, etc.           |
+-->| LINK to MONITOR MPU        |
| .                             |
+-----+
LINK
| MONITOR MPU task            |
+-----+
| CALL 'CRTMBX' USING         |
| NAME.                       |
| etc.                        |
| .                             |
+-----+
```

DS 620143300  
1 November 1985

```
| CALL 'CRTPRC' USING |  
|                      |  
|                      |  
|                      |  
+-----+  
| OSIIBM |  
+-----+
```

**NOTES:**

The job step task (the program specified in the EXEC statement in the JCL) is the MVS Initialization program (OSIMVSI). It GETMAINS a TWA for the task, LOADs the COMMON TABLE, and then searches the MODULE LOAD TABLE, the TASK ATTACH TABLE, and the PROGRAM LINK TABLE (which are tables within the COMMON TABLE load module) to determine what modules to load and tasks to attach to prepare the region for execution.


The last (or only) program, the initialization program, links to is the NTM Monitor AP.

The NTM Monitor AP creates the Monitor MPU task and then sends it messages for it to start the MPUs required, such as the COMM MPU and the QP and PIOS MPUs.

The Monitor AP also sends messages to the COMM MPU for it to start the COMMs for the VAX and the Honeywell Level 6.

At this point the system is initialized and is ready for message traffic.

SUBTASK HIERARCHY



The highest level task is the NTM Monitor AP. It receives control from the MVS initialization program (via a LINK) after the initialization program has started the Error Log Write subtask.

The NTM Monitor AP starts the Monitor MPU subtask, and the Monitor MPU starts the COMM MPU, THE QP MPU and the PIOS MPU

The COMM MPU starts COMM1 for communication with the VAX, and

DS 620143300  
1 November 1985

COMM2 for communication with the Honeywell Level 6.

The QP MPU starts one or more QPs (Query Processors), and the PIOS MPU starts one or more PIOS Pseudo-APs.

All the tasks mentioned above run all day until told to terminate, except the QPs and PIOS Pseudo-APs. These tasks are transactions initiated by input from a terminal operator and are repeatedly started and ended all day.

## APPENDIX C

### VTAM LOGIC FOR IHC

The following document describes the logic and the VTAM macros used by the OSIIHC module (IHC). IHC will communicate with a 3270 terminal (or host emulating a 3270 type terminal) using a half duplex flip flop (HDFP) protocol. This was chosen over a half duplex contention protocol because its use is more prevalent with 3270 terminals. Also, there is no mechanism for communicating contention situations to the calling program (COM) since they are not apparent at the time the SEND is issued. In HDFP protocol one logical unit (LU) is in send mode, and the other is in receive mode. Their respective states are switched when the sender sends a message with a change direction indicator.

#### 1. Initialize Logic

- A. Verify that the correct number of parameters were passed and that the event block has been initialized to zeros.
- B. Save the address of all control blocks in the TWA and move the terminal id into the TWA.
- C. If the TWA contains a nonzero pointer to the VTAM control block module (this indicates the port has already been initialized)
  1. Issue a CLSDST for the session.
  2. Close the ACB.
  3. Reset the VTAM control flags to their initial state.
  4. Delete the IHCEXT module.
  5. Go to step D.

else

1. Load the VTAM control block module that is associated with the port we are initializing and save its address in the TWA.

- D. Load the exit routine module (INCEXT) which will handle error responses and abnormal conditions such as TPEND and LOSTERM. Fill in the ACB exit list with the addresses of the exit routines that are contained in INCEXT.
  - E. Obtain storage to be used as send and receive buffers.
  - F. Establish a session with the remote station or an VTAM terminology secondary logical unit (SLU).
    - 1. Open the ACB.
    - 2. Issue a SETLOGON.
    - 3. Issue an OPNDST with OPTCD=ACQUIRE.
    - 4. Move the CID (session identifier) to an RPL.
    - 5. Set a flag indicating the session is in a between bracket state.
2. Send Logic
- A. Verify parameters and save the addresses of the EVTBLK and XMTBLK.
  - B. Verify that a receive is not outstanding.
  - C. Move the data from the XMTBLK to the send buffer, inserting the 3270 control characters to erase the buffer and leave the keyboard locked.
  - D. If between bracket flag is on
    - 1. Issue a bid, set a timer, and wait for a definite response. If the timer expires before a response is received, we exit with a wait timeout error. (Whenever IHC must wait for a response from the SLU, a timer is set and a wait timeout error may occur. However, no timer is set when IHC waits for VTAM to schedule an event.) If the SLU is in transmit mode, it will give a negative response and we will exit with a message indicating a bid.

failure

- 2 Issue a SEND containing the data to be transmitted. This SEND will have a begin bracket, no end bracket, and no change direction indicators set.
- 3 Turn off the flag indicating the session is between brackets.

else

- 1 If change direction flag (VTANCDIR) is on and the remote accepts data flow control requests
    - a Issue a session control (SESSIONC) macro with a CLEAR option
    - b Issue a SESSIONC macro with a START DATA TRAFFIC option
    - c Wait for a response.
  - 2 Issue SEND a with no begin bracket, no end bracket, no change direction and exception responses only. This send will contain the data to be transmitted.
  - 3 Wait for the SEND to be scheduled.
  - E Issue a SEND to erase 3270 buffer, unlock the keyboard and set the change direction indicator
  - F Turn on the change direction flag.
  - G Set successful return code and exit.
- 3 Receive Logic
- A Validate parameters and prime the EVTBLK and other areas
  - B Ensure that the 'receive outstanding' flag is not set and that the event number is not zero.
  - C If the return receive flag is set:

1. Discard the data.
2. Issue a SEND with erase write, change direction, and keyboard unlock.
- D. Issue an asynchronous receive, specifying that the ECB in the EVTRBLK is to be posted upon completion.
- E. Set 'receive outstanding' and event type- 'receive' in the EVTRBLK. Move the event number from the parameter list to the EVTRBLK.
- F. Set successful return code and exit.
- G. If definite response is requested by the SLU, send the appropriate positive response.
- H. Set successful return code and exit.
4. Get Logic
  - A. Validate parameters.
  - B. Check to see that the ECB has been posted and that the event type is 'receive'.
  - C. Move the data from the buffer to the RCVBLK stripping off the 3270 control characters.
  - D. Set the length field in the RCVBLK and reset the flag indicating event outstanding.
  - E. If the change direction flag is on, reset the change direction indicator. (We are now the sender)
  - F. Reset the ECB and RFL used for the receive.
  - G. If definite response is requested by the SLU, send the appropriate positive response.
  - H. Set successful return code and exit.
5. Cancel Logic
  - A. Validate parameters.

- B. Insure that either a 'receive' or 'returned receive' is outstanding.
- C. Issue a RESETSR, canceling all synchronous data flows.
- D. Wait for the RESETSR to be completed.
- E. Reset the receive RPL so that it may be reused.
- F. If this terminal accepts data flow control requests:
  - 1. Issue a SESSIONC with a CLEAR option.
  - 2. Issue a SESSIONC with a START DATA TRAFFIC option.
  - 3. Set the flag indicating we are between brackets.
- G. Turn off the change direction flag.
- H. Set successful return code and exit.

6. Terminate Logic

- A. Verify parameters.
- B. Zero control blocks.
- C. Issue a CLSDST to end the session.
- D. Close the ACB.
- E. Delete the VTAM control block module and exit routine module.
- F. Set successful return code and exit.

7. Response Exit

- A. If response is negative
  - 1. Format an error message and call ERRPRO to record the error.

2. Issue a SESSIONC with a CLEAR option to reinitialize the session.
3. If the SLU accepts data flow control requests, issue a SESSIONC with a START DATA TRAFFIC option. Wait for the response.
4. Turn on the between bracket flag.
5. Return to VTAM.
- B. If the response is positive (this should not happen)
  1. Format an error message and call ERRPRO to record it.
  2. Return to VTAM.
8. TPEND Exit Routine  
(VTAM has been terminated or our APPLID has been inactivated.)
  - A. Format an error message and call ERRPRO to record it.
  - B. Set the flag indicating TPEND. After this flag has been set, all calls to IHC except TRMLAN and INILAN will be rejected with an error indicating 'tpend'.
9. Losterm exit routine (line failure, buffer overflow, etc.)
  - A. Format an error message and call ERRPRO to record it.
  - B. Set the flag indicating LOSTTERM. After this flag has been set, all calls to IHC except TRMLAN and INILAN will be rejected.
  - C. Return to VTAM
10. Defining parameters associated with the SLU (remote port)

Each SLU (host or terminal) will hve a load module associated with it that will contain all the VTAM control blocks necessary to establish and maintain communications. This module will have the same name as the port id. It is created by the 'VTANBLKS' macro. For each remote port, one of these macros must be coded, assembled and link edited as re-entrant. The format of the macro is shown below.

```
VTANBLKS APPLID-XXXX,TRMID-YYYY,VTRESID-ZZZZ,  
WAIT-WNNNN
```

where

APPLID is the name of the VTAM applid. This applid must be authorized to acquire terminals. A separate applid must be defined in VTAM for each remote port.

TRMID is the port name that is passed by COM to the IHC program.

VTRESID is the VTAM resource id associated with the port (i.e., the label on the LU macro that defines this device.)

WAITV is the maximum time (in macro seconds) that the IHC program will wait for a response from the SLU. The default value is 10,000 or 10 seconds. It should be noted that this timeout value only applies to waiting for replies from the SLU. When it is necessary to wait for VTAM to schedule an event, there is no timeout.

Additionally, TFFLAG- hex value may be specified. This option is used to specify terminal characteristics. Currently, the only terminal characteristics defined are whether or not the terminal supports data flow control RU's and other characteristics of a terminal with a FM profile of 3 and a TS profile of 3. If this bit is off, the SLU is treated as a local, non-SNA 3270. The default value (on) is correct for remote 3274 and 3276 SNA terminals. If support for additional terminals is desired, this field may be expanded.

END

8-87

DTIC